
Chapter 3 Transport Layer

Computer Networking

A Top-Down Approach



A note on the use of these ppt slides:

We're making these slides freely available to all (faculty, students, readers). They're in PowerPoint form so you see the animations; and can add, modify, and delete slides (including this one) and slide content to suit your needs. They obviously represent a *lot* of work on our part. In return for use, we only ask the following:

- If you use these slides (e.g., in a class) that you mention their source (after all, we' d like people to use our book!)
- If you post any slides on a www site, that you note that they are adapted from (or perhaps identical to) our slides, and note our copyright of this material.

Thanks and enjoy! JFK/KWR

CAll material copyright 1996-2012 J.F Kurose and K.W. Ross, All Rights Reserved Computer Networking: A Top Down Approach 6th edition Jim Kurose, Keith Ross Addison-Wesley March 2012


Chapter 3: Transport Layer

Goals:

- understand principles behind transport layer services:
 - multiplexing, de-multiplexing
 - reliable data transfer
 - flow control
 - congestion control
- Iearn about Internet transport layer protocols:
 - UDP: connectionless transport
 - TCP: connection-oriented reliable transport
 - TCP congestion control

Transport services and protocols

- provide logical communication between app processes running on different hosts
- transport protocols run in end systems
 - <u>send side</u>: breaks app messages into <u>segments</u>, passes to network layer
 - <u>rcv side:</u> reassembles segments into messages, passes to app layer
- more than one transport protocol available to apps
 - Internet: TCP and UDP



Transport vs. network layer


- * network layer: logical <u>communication</u> <u>between hosts</u>
- transport layer: logical
 <u>communication</u>
 <u>between processes</u>
 [communication]
 [comm
 - relies on, enhances, network layer services

- household analogy:


- 12 kids in Ann's house sending letters to 12 kids in Bill's house:
- hosts = houses
- processes = kids
- app messages = letters in envelopes
- transport protocol = Ann and Bill who demux to inhouse siblings
- network-layer protocol = postal service

Internet transport-layer protocols

- reliable, in-order delivery (TCP)
 - congestion control
 - flow control
 - connection setup
- unreliable, unordered delivery: UDP
 - no-frills extension of "best-effort" IP
- services not available:
 - delay guarantees
 - bandwidth guarantees




Multiplexing/demultiplexing



How demultiplexing works

host receives IP datagrams

- each datagram has source IP address, destination IP address
- each datagram carries one transport-layer segment
- each segment has source, destination port number
- host uses IP addresses & port numbers to direct segment to appropriate socket



TCP/UDP segment format


Connectionless demultiplexing

- * recall: created socket has host-local port #: DatagramSocket mySocket1
 - = new DatagramSocket(12534);
- recall: when creating datagram to send into UDP socket, must specify
 - destination IP address
 - destination port #

- when host receives UDP segment:
 - checks destination port # in segment
 - directs UDP segment to socket with that port #

IP datagrams with same dest. port #, but different source IP addresses and/or source port numbers will be directed to same socket at dest.

Connectionless demux: example




Connection-oriented demux

- TCP socket identified by 4-tuple:
 - source IP address
 - source port number
 - dest IP address
 - dest port number
- demux: receiver uses all four values to direct segment to appropriate socket

- server host may support many simultaneous TCP sockets:
 - each socket identified by its own 4-tuple
- web servers have different sockets for each connecting client
 - non-persistent HTTP will have different socket for each request


Connection-oriented demux: example



dest port: 80 are demultiplexed to *different* sockets

Transport Layer 3-11

Connection-oriented demux: example




Connectionless Transport UDP: User Datagram Protocol [RFC 768]

- "no frills," "bare bones" Internet transport protocol
- "best effort" service,
 UDP segments may be:
 - Iost
 - delivered out-of-order to app
- connectionless:
 - no handshaking between UDP sender, receiver
 - each UDP segment handled independently of others

- UDP use:
 - streaming multimedia apps (loss tolerant, rate sensitive)
 - DNS
 - SNMP
- reliable transfer over UDP:
 - add reliability at application layer
 - application-specific error recovery!

UDP: segment header



UDP segment format

length, in bytes of UDP segment, including header

why is there a UDP? -

- no connection establishment (which can add delay)
- simple: no connection
 state at sender, receiver
- small header size
- no congestion control: UDP can blast away as fast as desired

UDP checksum

Goal: detect "errors" (e.g., flipped bits) in transmitted segment

sender:


- treat segment contents, including header fields, as sequence of 16-bit integers
- checksum: addition (one's complement sum) of segment contents
- sender puts checksum value into UDP checksum field

receiver:

- compute checksum of received segment
- check if computed checksum equals checksum field value:
 - NO error detected
 - YES no error detected. But maybe errors nonetheless? More later

Internet checksum: example


example: add two 16-bit integers



Note: when adding numbers, a carryout from the most significant bit needs to be added to the result

Principles of reliable data transfer

- important in application, transport, link layers
 - top-10 list of important networking topics!




(a) provided service

 characteristics of unreliable channel will determine complexity of reliable data transfer protocol (rdt)

Principles of reliable data transfer


- important in application, transport, link layers
 - top-10 list of important networking topics!



complexity of reliable data transfer protocol (rdt)


Principles of reliable data transfer(rdt)

- important in application, transport, link layers
 - top-10 list of important networking topics!



 characteristics of unreliable channel will determine complexity of reliable data transfer protocol (rdt)


Reliable data transfer: getting started



Reliable data transfer: getting started


we'll:

- incrementally develop sender, receiver sides of <u>r</u>eliable <u>d</u>ata <u>t</u>ransfer protocol (rdt)
- consider only unidirectional data transfer
 - but control info will flow on both directions!
- use finite state machines (FSM) to specify sender, receiver



rdt1.0: reliable transfer over a reliable channel

- underlying channel perfectly reliable
 - no bit errors
 - no loss of packets
- separate FSMs for sender, receiver:
 - sender sends data into underlying channel
 - receiver reads data from underlying channel



sender

receiver

rdt2.0: channel with bit errors


- underlying channel may flip bits in packet
 - checksum to detect bit errors
- * the question: how to recover from errors:

How do humans recover from "errors" during conversation?

rdt2.0: channel with bit errors

- underlying channel may flip bits in packet
 - checksum to detect bit errors
- * the question: how to recover from errors:
 - acknowledgements (ACKs): receiver explicitly tells sender that pkt received OK
 - negative acknowledgements (NAKs): receiver explicitly tells sender that pkt had errors
 - sender retransmits pkt on receipt of NAK
- new mechanisms in rdt2.0 (beyond rdt1.0):
 - error detection
 - feedback: control msgs (ACK,NAK) from receiver to sender

rdt2.0: FSM (Finite State Machine) specification




notcorrupt(rcvpkt)

extract(rcvpkt,data)


deliver_data(data)

udt_send(ACK)

rdt2.0: operation with no errors



rdt2.0: error scenario



rdt2.0 has a fatal flaw!

what happens if ACK/NAK corrupted?


- sender doesn't know what happened at receiver!
- can't just retransmit:
 possible duplicate

handling duplicates:


- sender retransmits current pkt if ACK/NAK corrupted
- sender adds sequence number to each pkt
- receiver discards (doesn't deliver up) duplicate pkt

stop and wait
 sender sends one packet,
 then waits for receiver
 response

rdt2.1: sender, handles garbled ACK/NAKs



rdt2.1: receiver, handles garbled ACK/NAKs



rdt2.1: discussion

sender:

- seq # added to pkt
- two seq. #'s (0,1) will suffice. Why?
- must check if received ACK/NAK corrupted
- twice as many states
 - state must "remember" whether "expected" pkt should have seq # of 0 or 1


receiver:

- must check if received packet is duplicate
 - state indicates whether
 0 or I is expected pkt
 seq #
- note: receiver can not know if its last ACK/NAK received OK at sender

rdt2.2: a NAK-free protocol

- same functionality as rdt2.1, using ACKs only
- instead of NAK, receiver sends ACK for last pkt received OK
 - receiver must explicitly include seq # of pkt being ACKed
- duplicate ACK at sender results in same action as NAK: retransmit current pkt

rdt2.2: sender, receiver fragments



rdt3.0 : channels with errors and loss

new assumption:


underlying channel can also lose packets (data, ACKs)

 checksum, seq. #, ACKs, retransmissions will be of help ... but not enough


What is that reasonable time ? And how do you determine it ?

approach: sender waits "reasonable" amount of time for ACK

- retransmits if no ACK received in this time
- if pkt (or ACK) just delayed (not lost):
 - retransmission will be duplicate, but seq. #'s already handles this
 - receiver must specify seq
 # of pkt being ACKed
- requires countdown timer









Transport Layer 3-36

rdt3.0 in action



(c) ACK loss



(d) premature timeout/ delayed ACK

Transport Layer 3-37

Performance of rdt3.0

rdt3.0 is correct, but performance stinks

e.g.: I Gbps link, I5 ms prop. delay, 8000 bit packet:

$$D_{trans} = \frac{L}{R} = \frac{8000 \text{ bits}}{10^9 \text{ bits/sec}} = 8 \text{ microsecs}$$


U sender: utilization – fraction of time sender busy sending

$$U_{\text{sender}} = \frac{L/R}{RTT + L/R} = \frac{.008}{30.008} = 0.00027$$

 if RTT=30 msec, IKB pkt every 30 msec: 33kB/sec thruput over I Gbps link

network protocol limits use of physical resources!


rdt3.0: stop-and-wait operation



Pipelined protocols

pipelining: sender allows multiple, "in-flight", yetto-be-acknowledged pkts

- range of sequence numbers must be increased
- buffering at sender and/or receiver




(a) a stop-and-wait protocol in operation

(b) a pipelined protocol in operation

two generic forms of pipelined protocols: go-Back-N, selective repeat

Pipelining: increased utilization



Pipelined protocols: overview

Go-back-N:

- sender can have up to N unacked packets in pipeline
- receiver only sends
 cumulative ack
 - doesn't ack packet if there's a gap
- sender has timer for oldest unacked packet
 - when timer expires, retransmit all unacked packets


Selective Repeat:

- sender can have up to N unack' ed packets in pipeline
- rcvr sends individual ack for each packet

- sender maintains timer
 for each unacked packet
 - when timer expires, retransmit only that unacked packet

Go-Back-N: sender

- k-bit seq # in pkt header
- "window" of up to N, consecutive unack' ed pkts allowed




ACK(n):ACKs all pkts up to, including seq # n - "cumulative ACK"


may receive duplicate ACKs (see receiver)

- timer for oldest in-flight pkt
- timeout(n): retransmit packet n and all higher seq # pkts in window

GBN: sender extended FSM (finite state machine)



GBN: receiver extended FSM



ACK-only: always send ACK for correctly-received pkt with highest *in-order* seq #

- may generate duplicate ACKs
- need only remember expectedseqnum
- out-of-order pkt:
 - discard (don' t buffer): <u>no receiver buffering!</u>
 - re-ACK pkt with highest in-order seq #

GBN in action


<u>sender window (I</u>	N=4) <u>sender</u>	receiver
<mark>0 1 2 3</mark> 4 5 6 7 8	send pkt0	
<mark>0 1 2 3</mark> 4 5 6 7 8	send pkt1	receive pkt0, send ack0
<mark>0 1 2 3</mark> <mark>4 5 6 7 8</mark>	send pkt2	
<mark>0 1 2 3</mark> 4 5 6 7 8	send pkt3	receive pkt1, send ack1
0 <mark>1234</mark> 5678	(wait) rcv ack0, send pkt4	receive pkt3, discard, (re)send ack1
	rcv ack1, send pkt5	
0 1 <mark>2 3 4 5 </mark> 6 7 8	icv acki, seliu pris	receive pkt4, discard,
	ignore duplicate ACK	(re)send ack1 receive pkt5, discard, (re)send ack1
0 1 <mark>2 3 4 5 </mark> 6 7 8	send pkt2	
0 1 <mark>2 3 4 5 </mark> 6 7 8	send pkt3	
0 1 <mark>2 3 4 5 </mark> 6 7 8	send pkt4	rcv pkt2, deliver, send ack2
0 1 <mark>2 3 4 5 </mark> 6 7 8	send pkt5	rcv pkt3, deliver, send ack3
		rcv pkt4, deliver, send ack4 rcv pkt5, deliver, send ack5
		ico pres, deliver, senu acro
		Transport Laver 3-46

Selective repeat

receiver individually acknowledges all correctly received pkts

- buffers pkts, as needed, for eventual in-order delivery to upper layer
- sender <u>only resends pkts</u> for which ACK not received
 - sender timer for each unACKed pkt
- sender window
 - N consecutive seq #' s
 - Iimits seq #s of sent, unACKed pkts

Selective repeat: sender, receiver windows



Selective repeat

- sender

data from above:

 if next available seq # in window, send pkt

timeout(n):

 resend pkt n, restart timer

ACK(n) in [sendbase,sendbase+N]:

- mark pkt n as received
- if n smallest unACKed
 pkt, advance window base
 to next unACKed seq #

– receiver

pkt n in [rcvbase, rcvbase+N-1]

- send ACK(n)
- out-of-order: buffer
- in-order: deliver (also deliver buffered, in-order pkts), advance window to next not-yet-received pkt


pkt n in [rcvbase-N,rcvbase-1]

ACK(n)

otherwise:

ignore

Selective repeat in action window size =4




Selective repeat: dilemma

example:

- ✤ seq #' s: 0, 1, 2, 3
- window size=3
- receiver sees no difference in two scenarios!
- duplicate data accepted as new in
 (b) .. BECAUSE Rx doesn't know about LOST NAKs.
- Q: what relationship between seq # size and window size to avoid problem in (b)?

sender window receiver window (after receipt) (after receipt) 0123012 0123012 0123012 0 1 2 3 0 1 2 **/ pkt3** 0 1 2 3 0 1 2 🗲 pkt0 will accept packet with seq number 0 (a) no problem

receiver can't see sender side. receiver behavior identical in both cases! something's (very) wrong!



Transport Layer 3-51

Chapter 3 outline

- 3.1 transport-layer services
- 3.2 multiplexing and demultiplexing
- 3.3 connectionless transport: UDP
- 3.4 principles of reliable data transfer


- 3.5 connection-oriented transport: TCP
 - segment structure
 - reliable data transfer
 - flow control
 - connection management
- 3.6 principles of congestion control
- 3.7 TCP congestion control

- point-to-point:
 - one sender, one receiver
- reliable, in-order byte steam:
 - no "message boundaries"
- pipelined:
 - TCP congestion and flow control set window size

full duplex data:

- bi-directional data flow in same connection
- MSS: maximum segment size
- connection-oriented:
 - handshaking (exchange of control msgs) inits sender, receiver state before data exchange
- flow controlled:
 - sender will not overwhelm receiver

TCP segment structure



TCP seq. numbers, ACKs


sequence numbers:

byte stream "number" of first byte in segment's data


acknowledgements:

- seq # of next byte expected from other side
- cumulative ACK
- Q: how receiver handles out-oforder segments
 - A: TCP spec doesn't say,
 - up to implementor

outgoing segment from sender



TCP seq. numbers, ACKs



simple telnet scenario

TCP round trip time, timeout

- <u>Q</u>: how to set TCP timeout value?
- Ionger than RTT
 - but RTT varies
- too short: premature timeout, unnecessary retransmissions
- too long: slow
 reaction to segment
 loss


<u>Q:</u> how to estimate RTT?

- SampleRTT: measured time from segment transmission until ACK receipt
 - ignore retransmissions
- SampleRTT will vary, want estimated RTT "smoother"
 - average several recent measurements, not just current SampleRTT

TCP round trip time, timeout

EstimatedRTT = $(1 - \alpha)$ *EstimatedRTT + α *SampleRTT

- exponential weighted moving average
- influence of past sample decreases exponentially fast
- \star typical value: $\alpha = 0.125$ (RFC 2119)



TCP round trip time, timeout

* timeout interval: EstimatedRTT plus "safety margin"

- Iarge variation in EstimatedRTT -> larger safety margin
- stimate SampleRTT deviation from EstimatedRTT: (RFC 6298)

DevRTT = $(1-\beta)$ *DevRTT +

 β *|SampleRTT-EstimatedRTT|

RTT Variation: as an estimate of how much SampleRTT typically (typically, $\beta = 0.25$) deviates from EstimatedRTT:

TimeoutInterval = EstimatedRTT + 4*DevRTT estimated RTT "safety margin"

TCP reliable data transfer

- TCP creates rdt service on top of IP's unreliable service
 - pipelined segments
 - cumulative acks
 - single retransmission timer
- retransmissions triggered by:
 - timeout events
 - duplicate acks

let's initially consider simplified TCP sender:

- ignore duplicate acks
- ignore flow control, congestion control

TCP sender events:


data rcvd from app:

- create segment with seq #
- seq # is byte-stream number of first data byte in segment
- start timer if not already running
 - think of timer as for oldest unacked segment
 - expiration interval: TimeOutInterval


timeout:

- retransmit segment
 that caused timeout
- restart timer
 ack rcvd:
- if ack acknowledges previously unacked segments
 - update what is known to be ACKed
 - start timer if there are still unacked segments


TCP sender (simplified)



TCP: retransmission scenarios



TCP: retransmission scenarios



TCP ACK generation [RFC 1122, RFC 2581]


event at receiver	TCP receiver action
arrival of in-order segment with expected seq #. All data up to expected seq # already ACKed	delayed ACK. Wait up to 500ms for next segment. If no next segment, send ACK
arrival of in-order segment with expected seq #. One other segment has ACK pending	immediately send single cumulative ACK, ACKing both in-order segments
arrival of out-of-order segment higher-than-expect seq. # . Gap detected	immediately send <i>duplicate ACK</i> , indicating seq. # of next expected byte
arrival of segment that partially or completely fills gap	immediate send ACK, provided that segment starts at lower end of gap

TCP fast retransmit

- time-out period often relatively long:
 - long delay before resending lost packet
- detect lost segments via duplicate ACKs.
 - sender often sends many segments backto-back
 - if segment is lost, there will likely be many duplicate ACKs.


- TCP fast retransmit if sender receives 3 ACKs for same data ("triple duplicate ACKs"), resend unacked segment with smallest seq #
 - likely that unacked segment lost, so don't wait for timeout

TCP fast retransmit




Transport Layer 3-67

TCP flow control



TCP flow control


- receiver "advertises" free buffer space by including rwnd (receiver window) value in TCP header of receiver-to-sender segments.
 - RcvBuffer size set via socket options (typical default is 4096 bytes)
 - many operating systems autoadjust RcvBuffer
- sender limits amount of unacked ("in-flight") data to receiver's rwnd value
- guarantees receive buffer will not overflow




Connection Management

before exchanging data, sender/receiver "handshake":

- agree to establish connection (each knowing the other willing to establish connection)
- agree on connection parameters






Socket connectionSocket =
welcomeSocket.accept();

Agreeing to establish a connection

2-way handshake:




Q: will 2-way handshake always work in network?


- variable delays
- retransmitted messages
 (e.g. req_conn(x)) due to message loss
- message reordering
- can' t "see" other side

Agreeing to establish a connection


2-way handshake failure scenarios:



TCP 3-way handshake



TCP 3-way handshake: FSM




TCP: closing a connection

client, server each close their side of connection

- send TCP segment with FIN bit = I
- respond to received FIN with ACK
 - on receiving FIN, ACK can be combined with own FIN
- simultaneous FIN exchanges can be handled

TCP: closing a connection




Principles of congestion control

congestion:

- informally: "too many sources sending too much data too fast for network to handle"
- different from flow control!
- manifestations:
 - Iost packets (buffer overflow at routers)
 - Iong delays (queueing in router buffers)
- a top-10 problem!


original data: λ_{in} throughput: λ_{out} two senders, two ** receivers Host A one router, infinite ** unlimited shared buffers output link buffers output link capacity: R * no retransmission * Host B R/2 delay λ_{out} λ_{in} λ_{in} R/2 R/2 large delays as arrival rate, λ_{in} , maximum per-connection * * approaches capacity throughput: R/2


- one router, *finite* buffers
- sender retransmission of timed-out packet
 - application-layer input = application-layer output: λ_{in} = λ_{out}
 - transport-layer input includes retransmissions : $\lambda_{in} \ge \lambda_{in}$





 sender sends only when router buffers available







Idealization: known loss

packets can be lost, dropped at router due to full buffers

 sender only resends if packet known to be lost






 sender only resends if packet known to be lost


Α


Host B



Realistic: duplicates


- packets can be lost, dropped at router due to full buffers
- sender times out prematurely, sending two copies, both of which are delivered





Realistic: duplicates

- packets can be lost, dropped at router due to full buffers
- sender times out prematurely, sending two copies, both of which are delivered




"costs" of congestion:


- more work (retrans) for given "goodput"
- unneeded retransmissions: link carries multiple copies of pkt
 - decreasing goodput

- four senders
- multihop paths
- timeout/retransmit

<u>Q</u>: what happens as λ_{in} and λ_{in} increase ?

A: as red λ_{in} increases, all arriving blue pkts at upper queue are dropped, blue throughput $\rightarrow 0$





another "cost" of congestion:

when packet dropped, any "upstream transmission capacity used for that packet was wasted!

Approaches towards congestion control

two broad approaches towards congestion control:

end-end congestion _ control:

- no explicit feedback from network
- congestion inferred from end-system observed loss, delay
- approach taken by TCP

network-assisted congestion control:

- routers provide feedback to end systems
 - single bit indicating congestion (SNA, DECbit, TCP/IP ECN, ATM)
 - explicit rate for sender to send at

Case study: ATM ABR congestion control

ABR: available bit rate:


- "elastic service": <u>meaning</u> rate can be changed reacting to traffic
- if sender's path
 <u>underloaded</u>":
 - sender should use available bandwidth
- if sender's path
 <u>congested:</u>
 - sender throttled to minimum guaranteed rate

RM (resource management) cells:

- sent by sender, interspersed with data cells
- bits in RM cell set by switches ("network-assisted")
 - NI bit: no increase in rate (mild congestion)
 - Cl bit: congestion indication

 RM cells returned to sender by receiver, with bits intact


Case study: ATM ABR congestion control



- two-byte ER (explicit rate) field in RM cell
 - congested switch may lower ER value in cell because we added RM cells
 - senders' send rate thus max supportable rate on path
- EFCI bit in data cells: set to 1 in congested switch
 - if data cell preceding RM cell has EFCI set, receiver sets CI bit in returned RM cell


TCP congestion control: additive increase multiplicative decrease

- *approach*: sender increases transmission rate (window size), probing for usable bandwidth, until loss occurs
 - additive increase: increase cwnd by I MSS every RTT until loss detected
 - multiplicative decrease: cut cwnd in half after loss



additively increase window size ...

TCP Congestion Control: details




sender limits transmission:

LastByteSent-LastByteAcked ≤ cwnd

 cwnd is dynamic, function of perceived network congestion


TCP sending rate:

 roughly: send cwnd bytes, wait RTT for ACKS, then send more bytes



TCP Slow Start

- when connection begins, increase rate exponentially until first loss event:
 - initially cwnd = I MSS (Max Seg Size)
 - double cwnd every RTT
 - done by incrementing cwnd for every ACK received
- summary: initial rate is slow but ramps up exponentially fast: 1,2,4,8,16



TCP: detecting, reacting to loss

Ioss indicated by timeout:

cwnd set to I MSS;

- window then grows exponentially (as in slow start) to threshold, then grows linearly
- Ioss indicated by 3 duplicate ACKs: TCP RENOincorporated fast recovery
 - dup ACKs indicate network capable of delivering some segments
 - cwnd is cut in half window then grows linearly
- TCP Tahoe always sets cwnd to 1 (timeout or 3 duplicate acks)


TCP: switching from slow start to CA

- Q:When should the exponential increase switch to linear?
- A:When **cwnd** gets to 1/2 of its value before timeout.


Implementation:

- variable ssthresh
- on loss event, ssthresh, is set to 1/2 of cwnd just before loss event





Summary: TCP Congestion Control



Transport Layer 3-95

TCP throughput

* avg. TCP thruput as function of window size, RTT?

- ignore slow start, assume always data to send
- W: window size (measured in bytes) where loss occurs
 - avg. window size (# in-flight bytes) is ³/₄ W
 - avg. thruput is 3/4W per RTT

avg TCP thruput =
$$\frac{3}{4} \frac{W}{RTT}$$
 bytes/sec

TCP Futures: TCP over "long, fat pipes"

- example: 1500 byte segments, 100ms
 RTT, want 10 Gbps throughput
- requires W = 83,333 in-flight segments
- throughput in terms of segment loss probability, L [Mathis 1997]:

CP throughput =
$$\frac{1.22 \cdot MSS}{RTT \sqrt{L}}$$

→ to achieve 10 Gbps throughput, need a loss rate of L = 2.10-10 – a very small loss rate!

Throughput = $\frac{3}{4}$ (W/RTT) Throughput = 10Gbps RTT = 100msec 1 byte = 8 bits RTT = Return Path

```
W = Throughput * 4/3* RTT
= 1333333.333
```

Then divided by 8 for size in bits

```
W = 1333333.333/8 = 16666666.667
```


```
Then divided by 2 for segments travelling one-way only
```

W = 1666666.667/2 = 83,333.33

new versions of TCP for high-speed




fairness goal: if K TCP sessions share same bottleneck link of bandwidth R, each should have average rate of R/K



Why is TCP fair?

two competing sessions:

- additive increase gives slope of I, as throughout increases
- multiplicative decrease decreases throughput proportionally



Fairness (more)

Fairness and UDP

- multimedia apps often do not use TCP
 - do not want rate throttled by congestion control
- instead use UDP:
 - send audio/video at constant rate, tolerate packet loss

Fairness, parallel TCP connections

- application can open multiple parallel connections between two hosts
- web browsers do this
- e.g., link of rate R with 9 existing connections:
 - new app asks for I TCP, gets rate R/10
 - new app asks for 11 TCPs, gets R/2

Chapter 3: summary

- principles behind transport layer services:
 - multiplexing, demultiplexing
 - reliable data transfer
 - flow control
 - congestion control
- instantiation,
 implementation in the
 Internet
 - UDP
 - TCP

next:

- leaving the network "edge" (application, transport layers)
- into the network "core"